

# OPCIÓN 1: Instalar Autopsy en Ubuntu o Debian (recomendado)

## Requisitos previos

Instalar Java, SleuthKit y dependencias necesarias:

```
sudo apt update  
sudo apt install sleuthkit openjdk-11-jdk unzip wget -y
```


## 1. Descargar Autopsy

```
cd /opt  
sudo wget https://github.com/sleuthkit/autopsy/releases/download/autopsy-4.21.0/  
autopsy-4.21.0.zip  
sudo unzip autopsy-4.21.0.zip  
sudo chmod -R +x autopsy-4.21.0
```

 Puedes consultar la [última versión en GitHub](#)

## 2. Ejecutar Autopsy

```
cd /opt/autopsy-4.21.0/bin  
./autopsy
```

 Se abrirá un servidor local y te mostrará una URL como:

Starting Autopsy...

```
~ > sudo autopsy  
[sudo] password for kali:  
  
=====
```

Autopsy Forensic Browser  
<http://www.sleuthkit.org/autopsy/>  
ver 2.24

```
=====
```


Evidence Locker: /var/lib/autopsy  
Start Time: Wed Nov 5 08:22:54 2025  
Remote Host: localhost  
Local Port: 9999


Open an HTML browser on the remote host and paste this URL in it:

<http://localhost:9999/autopsy>

Keep this process running and use <ctrl-c> to exit

Open your browser to <http://localhost:9999/autopsy>

 Abre esa URL en tu navegador y ¡listo!



 ¿Quieres un acceso directo en el escritorio?

Crea un lanzador .desktop:

```
nano ~/.local/share/applications/autopsy.desktop
```

Y pega:

```
[Desktop Entry]
Name=Autopsy
Exec=/opt/autopsy-4.21.0/bin/autopsy
Icon=utilities-terminal
Terminal=true
Type=Application
Categories=Utility;
Guarda con CTRL+O y sal con CTRL+X.
```

## ✓ OPCIÓN 2 (alternativa): Ejecutar con Docker

Si no quieres instalar nada en el sistema:

```
docker pull rmoriz/autopsy
```

```
docker run -it -p 9999:9999 rmoriz/autopsy
```

Luego abre en navegador: <http://localhost:9999/autopsy>

The screenshot shows the 'CREATE A NEW CASE' form. It has three main sections: 1. Case Name, 2. Description, and 3. Investigator Names. The Case Name field contains '0000002'. The Description field contains 'Autopsiando un algo'. The Investigator Names section has ten fields labeled a. through j., with 'Cristóbal J.' entered in field a. At the bottom are three buttons: 'NEW CASE', 'CANCEL', and 'HELP'.

**CREATE A NEW CASE**

1. **Case Name:** The name of this investigation. It can contain only letters, numbers, and symbols.

2. **Description:** An optional, one line description of this case.

3. **Investigator Names:** The optional names (with no spaces) of the investigators for this case.

a.	<input type="text" value="Cristóbal J."/>	b.	<input type="text"/>
c.	<input type="text"/>	d.	<input type="text"/>
e.	<input type="text"/>	f.	<input type="text"/>
g.	<input type="text"/>	h.	<input type="text"/>
i.	<input type="text"/>	j.	<input type="text"/>

**NEW CASE** **CANCEL** **HELP**

UNA VEZ CREADO EL CASO

The screenshot shows the Autopsy web interface after a case has been created. The URL in the browser is 'http://localhost:9999/autopsy?mod=0&view=2&case=0000002'. The page title is 'Creating Case: 0000002'. The text on the page says: 'Case directory (/var/lib/autopsy/0000002/) created', 'Configuration file (/var/lib/autopsy/0000002/case.aut) created', and 'We must now create a host for this case.' At the bottom is a button labeled 'ADD HOST'.

<http://localhost:9999/autopsy?mod=0&view=2&case=0000002>

**Creating Case: 0000002**

Case directory (/var/lib/autopsy/0000002/) created  
Configuration file (/var/lib/autopsy/0000002/case.aut) created

We must now create a host for this case.

**ADD HOST**

## EL SIGUIENTE PASO

Case: 0000002

ADD A NEW HOST

1. **Host Name:** The name of the computer being investigated. It can contain only letters, numbers, and symbols.

2. **Description:** An optional one-line description or note about this computer.

3. **Time zone:** An optional timezone value (i.e. EST5EDT). If not given, it defaults to the local setting. A list of time zones can be found in the help files.

4. **Timeskew Adjustment:** An optional value to describe how many seconds this computer's clock was out of sync. For example, if the computer was 10 seconds fast, then enter -10 to compensate.

5. **Path of Alert Hash Database:** An optional hash database of known bad files.

6. **Path of Ignore Hash Database:** An optional hash database of known good files.

Rellenamos con estos datos

### Relleno rápido recomendado (para empezar ya)

- **Host Name:** host1
- **Description:** práctica de laboratorio
- **Time zone:** (vacío) o UTC
- **Timeskew:** 0
- **Alert Hash DB:** (vacío)
- **Ignore Hash DB:** (vacío)

Luego **Create Host** → y en el siguiente paso añades la **imagen forense** (Add Image), eliges el **tipo** (raw/dd/E01), marcas **verify** si quieres, y continúas con el análisis (File Analysis, Keyword Search, Timeline, etc.). Ahora añadimos una imagen

**Adding host: host1 to case 0000001**

Host Directory (/var/lib/autopsy/0000001/host1/) created

Configuration file (/var/lib/autopsy/0000001/host1/host.aut) created

We must now import an image file for this host

Puedes descargar imágenes de disco o crear una, por ejemplo:

```
# 1) Crear un "disco" vacío de 100 MB
dd if=/dev/zero of=lab.img bs=1M count=100

# 2) Formatearlo (ext4; vale cualquier FS que quieras probar)
mkfs.ext4 lab.img

# 3) Montarlo en loop y meter "evidencias"
sudo mkdir -p /mnt/labimg
sudo mount -o loop lab.img /mnt/labimg
sudo mkdir -p /mnt/labimg/docs
sudo cp /etc/hosts /mnt/labimg/docs/hosts.txt
echo "nota secreta" | sudo tee /mnt/labimg/docs/nota.txt >/dev/null

# 4) Desmontar
sudo umount /mnt/labimg

# (Opcional) Calcular hashes para la cadena de custodia
md5sum lab.img
sha1sum lab.img
```

```
~/Documents/box > dd if=/dev/zero of=lab.img bs=1M count=100
100+0 records in
100+0 records out
104857600 bytes (105 MB, 100 MiB) copied, 0.369066 s, 284 MB/s
~/Documents/box > mkfs.ext4 lab.img
mke2fs 1.47.2 (1-Jan-2025)
Discarding device blocks: done
Creating filesystem with 102400 1k blocks and 25584 inodes
Filesystem UUID: e4033dd8-061c-465f-8b1e-d8c793ce8bc4
Superblock backups stored on blocks:
    8193, 24577, 40961, 57345, 73729

Allocating group tables: done
Writing inode tables: done
Creating journal (4096 blocks): done
Writing superblocks and filesystem accounting information: done
```

```
~/Documents/box > sudo mkdir -p /mnt/labimg
[sudo] password for kali:
~/Documents/box > sudo mount -o loop lab.img /mnt/labimg
~/Documents/box > sudo mkdir -p /mnt/labimg/docs
~/Documents/box > sudo cp /etc/hosts /mnt/labimg/docs/hosts.txt
~/Documents/box > echo "nota secreta" | sudo tee /mnt/labimg/docs/nota.txt >/dev/null
~/Documents/box > sudo umount /mnt/labimg
~/Documents/box > md5sum lab.img
e72369116528a3aa03e12d4f109d7155 lab.img
~/Documents/box > sha1sum lab.img
0d08444f37ab9456834fc460c3cbc0199675964b lab.img
~/Documents/box > |
```

y ahora

❑ Haz clic en el botón **“Add Image File”**  
(justo en el centro de la pantalla que muestras).

❑ En la nueva ventana que aparece:

- **Image Type:** selecciona  
👉 Single, raw (dd)  
(porque creaste una imagen con dd, que es formato raw)
- **Image File Path:**  
pulsas el botón **Browse** y selecciona tu archivo lab.img.  
📁 Si lo hiciste en tu carpeta personal, estará en:
  - /home/tu\_usuario/lab.img

(ajusta el nombre del usuario según corresponda).

**ADD A NEW IMAGE**

**1. Location**  
Enter the full path (starting with /) to the image file.  
If the image is split (either raw or EnCase), then enter "\*" for the extension.

**2. Type**  
Please select if this image file is for a disk or a single partition.  
☒ Disk ☐ Partition

**3. Import Method**  
To analyze the image file, it must be located in the evidence locker. It can be imported from its current location using a symbolic link, by copying it, or by moving it. Note that if a system failure occurs during the move, then the image could become corrupt.  
☒ Symlink ☐ Copy ☐ Move

**NEXT** **CANCEL** **HELP**

**Warning:** Autopsy could not determine the volume system type for the disk image (i.e. the type of partition table). Please select the type from the list below or reclassify the image as a volume image instead of as a disk image.

Disk Image ☐ Volume Image ☒

Volume System Type (disk image only):

**OK**

Pulsamos en volumen image

### Image File Details

**Local Name:** images/lab.img

**Data Integrity:** An MD5 hash can be used to verify the integrity of the image.  
(With split images, this hash is for the full image file)

☒ Ignore the hash value for this image.

☐ Calculate the hash value for this image.

☐ Add the following MD5 hash value for this image:

☐ Verify hash after importing?

### File System Details

Analysis of the image file shows the following partitions:

Partition 1 (Type: ext4)

Mount Point:  File System Type:

ADD

CANCEL

HELP

Testing partitions  
Linking image(s) into evidence locker  
Image file added with ID `img1`  
Volume image (0 to 0 - ext - /1/) added with ID `vol1`

OK

ADD IMAGE

Pulsa en add

Select a volume to analyze or add a new image file.

CASE GALLERY

HOST GALLERY

HOST MANAGER

mount	name	fs type	
<input checked="" type="radio"/> /1/	lab.img-0-0	ext	<a href="#">details</a>

ANALYZE

ADD IMAGE FILE

CLOSE HOST

HELP

FILE ACTIVITY TIME LINES

IMAGE INTEGRITY

HASH DATABASES

VIEW NOTES

EVENT SEQUENCER

Elegimos el tipo de análisis

### File Activity Timelines

Here you can create a timeline of file activity.  
This process requires two steps:

1. **Create Data File** from file system data -> 2. **Create Timeline** from the data file

Use the tabs above to start.

Here we will process the file system images, collect the temporal data, and save the data to a single file.

1. Select one or more of the following images to collect data from:

☒ /1/ lab.img-0-0 ext

2. Select the data types to gather:

☒ Allocated Files ☒ Unallocated Files

3. Enter name of output file (body):

output/

4. Generate MD5 Value? ☒

Running `fls -r -m on vol1`

Body file saved to `/var/lib/autopsy/0000002/host1/output/body`

Entry added to host config file

Calculating MD5 Value

MD5 Value: 448B33AE589C3BAAE37AD1874FD57492

The next step is to sort the data into a timeline.



Now we will sort the data and save it to a timeline.

1. Select the data input file (body):

☒ body

2. Enter the starting date:

None: ☒

Specify: ☐ Nov  2025

3. Enter the ending date:

None: ☒

Specify: ☐ Nov  2025

4. Enter the file name to save as:

output/

5. Select the UNIX image that contains the /etc/passwd and /etc/group files:

6. Choose the output format:

- ☒ Tabulated (normal)  
☐ Comma delimited with hourly summary  
☐ Comma delimited with daily summary

7. Generate MD5 Value? ☒

[<- Oct 2025](#) [Summary](#) [Dec 2025 ->](#)

Nov

Wed Nov 05 2025 08:34:12	12288	macb	d/drwx-----	0	0	11	/1/lost+found
Wed Nov 05 2025 08:35:00	1024	...b	d/drwxr-xr-x	0	0	13	/1/docs
Wed Nov 05 2025 08:35:07	1024	.a..	d/drwxr-xr-x	0	0	13	/1/docs
	148	macb	r/rrw-r--r--	0	0	14	/1/docs/hosts.txt
Wed Nov 05 2025 08:35:12	1024	m.c.	d/drwxr-xr-x	0	0	13	/1/docs
	13	macb	r/rrw-r--r--	0	0	15	/1/docs/nota.txt

```
~/Documents/box > cat /var/lib/autopsy/00000002/host1/output/timeline.txt
Wed Nov 05 2025 08:34:12 12288 macb d/drwx----- 0 0 11 /1/lost+found
Wed Nov 05 2025 08:35:00 1024 ...b d/drwxr-xr-x 0 0 13 /1/docs
Wed Nov 05 2025 08:35:07 1024 .a.. d/drwxr-xr-x 0 0 13 /1/docs
148 macb r/rrw-r--r-- 0 0 14 /1/docs/hosts.tx
t
Wed Nov 05 2025 08:35:12 1024 m.c. d/drwxr-xr-x 0 0 13 /1/docs
13 macb r/rrw-r--r-- 0 0 15 /1/docs/nota.txt
~/Documents/box > |
```

file:///var/lib/autopsy/0000002/host1/output/sorter-vol1/text.html

## text Category

/1/docs/hosts.txt

ASCII text

Image: /var/lib/autopsy/0000002/host1/images/lab.img Inode: 14

/1/docs/nota.txt

ASCII text

Image: /var/lib/autopsy/0000002/host1/images/lab.img Inode: 15

http://localhost:9999/autopsy?mod=2&view=8&case=0000002&host=host1&inv=unknov

ASCII ([display](#) - [report](#)) \* Hex ([display](#) - [report](#)) \* ASCII Strings ([display](#) - [rep](#)  
File Type: ASCII text

Contents Of File: /1/vol1-meta-15

nota secreta

FILE SYSTEM IMAGES	
lab.img	<input type="button" value="CALCULATE"/>
TIMELINE DATA FILES	
body 448B33AE589C3BAAE37AD1874FD57492	<input type="button" value="VALIDATE"/>
TIMELINE	
timeline.txt 0203E360AC24C0CAF42B74FE2841B300	<input type="button" value="VALIDATE"/>
<input type="button" value="CLOSE"/> <input type="button" value="REFRESH"/> <input type="button" value="HELP"/>	

Original MD5: 0203E360AC24C0CAF42B74FE2841B300  
Current MD5: 0203E360AC24C0CAF42B74FE2841B300  
Pass

## General File System Details

### FILE SYSTEM INFORMATION

File System Type: Ext4  
Volume Name:  
Volume ID: c48bce93c7d81e8b5f461c06d83d03e4

Last Written at: 2025-11-05 08:35:21 (CET)  
Last Checked at: 2025-11-05 08:34:12 (CET)

Last Mounted at: 2025-11-05 08:34:52 (CET)  
Unmounted properly  
Last mounted on: /mnt/labimg

Source OS: Linux  
Dynamic Structure  
Compat Features: Journal, Ext Attributes, Resize Inode, Dir Index  
InCompat Features: Filetype, Extents, 64bit, Flexible Block Groups,  
Read Only Compat Features: Sparse Super, Large File, Huge File, Extra Inode Size

Journal ID: 00  
Journal Inode: 8

Current Directory: [./](#)

ADD NOTE

GENERATE MD5 LIST OF FILES

DEL	Type	NAME	WRITTEN	ACCESSED	CHANGED	SIZE	UID	GID	MET
	<a href="#">dir</a> / <a href="#">in</a>								
Error Parsing File (Invalid Characters?): V/V 25585: \$OrphanFiles 0000-00-00 00:00:00 (UTC) 0000-00-00 00:00:00 (UTC) 0000-00-00 00:00:00 (UTC) 0000-00-00 00:00:00 (UTC) 0 0 0									
	d / d	<a href="#">../</a>	2025-11-05 08:35:00 (CET)	2025-11-05 08:35:00 (CET)	2025-11-05 08:35:00 (CET)	1024	0	0	<a href="#">2</a>
	d / d	<a href="#">./</a>	2025-11-05 08:35:00 (CET)	2025-11-05 08:35:00 (CET)	2025-11-05 08:35:00 (CET)	1024	0	0	<a href="#">2</a>
	d / d	<a href="#">docs/</a>	2025-11-05 08:35:12 (CET)	2025-11-05 08:35:07 (CET)	2025-11-05 08:35:12 (CET)	1024	0	0	<a href="#">13</a>
	d / d	<a href="#">lost+found/</a>	2025-11-05 08:34:12 (CET)	2025-11-05 08:34:12 (CET)	2025-11-05 08:34:12 (CET)	12288	0	0	<a href="#">11</a>

3 hits- [link to results](#)

0 hits

[New Search](#)

3 occurrences of nota were found

### Search Options:

ASCII

## Case Sensitive

### Fragment 6727 (Hex - Ascii)

1: 52 (nota.txt)

### Fragment 8706 (Hex - Ascii)

2: 0 (nota secr)

### Fragment 49167 ([Hex](#) - [Ascii](#))

3: 52 (nota.txt)

nota was not found

### Search Options:

Unicode

## Case Sensitive

← PREVIOUS

**NEXT** ➡

EXPORT CONTENTS

ADD NOTE

ASCII (display - report) \* Hex (display - report) \* ASCII S

**File Type:** data

Fragment: 8706

**Status:** Allocated

**Group: 1**

### Find Meta Data Address

ASCII Contents of Fragment 8706 in lab.img-0-0

nota secreta

Current Directory: [/1/](#) /docs/

ADD NOTE

### GENERATE MD5 LIST OF FILES

DEL	Type <a href="#">dir</a> / <a href="#">in</a>	NAME🔍	WRITTEN	ACCESSED	CHANGED	S
	d / d	<a href="#">../</a>	2025-11-05 08:35:00 (CET)	2025-11-05 08:35:00 (CET)	2025-11-05 08:35:00 (CET)	1
	d / d	<a href="#">../</a>	2025-11-05 08:35:12 (CET)	2025-11-05 08:35:07 (CET)	2025-11-05 08:35:12 (CET)	1
	r / r	<a href="#">hosts.txt</a>	2025-11-05 08:35:07 (CET)	2025-11-05 08:35:07 (CET)	2025-11-05 08:35:07 (CET)	1
	r / r	<a href="#">nota.txt</a>	2025-11-05 08:35:12 (CET)	2025-11-05 08:35:12 (CET)	2025-11-05 08:35:12 (CET)	1

ASCII (display - report) \* Hex (display - report) \* ASCII Strings (display - report)

File Type: ASCII text

Contents Of File: /1/docs/hosts.txt

```
127.0.0.1      localhost
127.0.1.1      kali
::1            localhost ip6-localhost ip6-loopback
ff02::1        ip6-allnodes
ff02::2        ip6-allrouters
10.0.2.15      example.com
```

# SOLUCIONES SI DA PROBLEMAS EL LOG

## 1) Diagnóstico rápido (ejecuta en la misma terminal donde lanzaste Autopsy)

# ¿Dónde estás ejecutando Autopsy?

```
pwd
```

# ¿qué usuario eres?

```
whoami
```

# listar permisos del directorio donde está el binario/los scripts

```
ls -ld /usr/share/autopsy
```

```
ls -l /usr/share/autopsy/autopsy.log 2>/dev/null
```

# comprobar permisos del Evidence Locker (ya lo muestra el arranque)

```
ls -ld /var/lib/autopsy
```

Si `ls -l /usr/share/autopsy/autopsy.log` muestra "No such file or directory" o el directorio `/usr/share/autopsy` no es escribible por tu usuario, ahí está el problema.

---

## 2) Solución 1 — Crear el fichero de log y dar permisos (rápido y seguro)

Si quieres que el log exista en `/usr/share/autopsy` (donde parece buscarlo):

```
sudo touch /usr/share/autopsy/autopsy.log
```

```
sudo chown $(whoami):$(whoami) /usr/share/autopsy/autopsy.log
```

```
sudo chmod 644 /usr/share/autopsy/autopsy.log
```

Después reinicia Autopsy (o vuelve a lanzar el comando que usaste). Si el proceso corre como root, podrías en su lugar asignarlo al usuario que ejecute Autopsy.

---

## 3) Solución 2 — Ejecutar Autopsy con privilegios (si estás en entorno de pruebas)

Si no te importa ejecutar como root (solo en laboratorio):

```
sudo autopsy
```

# o si lo lanzaste con java:

```
sudo java -jar /usr/share/autopsy/bin/autopsy.jar
```